

BFBC2 MASTER SERVER EMULATOR v0.8 + Dedicated SERVER R34 All facts in one: This emulator does... ..not require any serial number! ...not require online(WAN) connections! ...not require any connection to nexus! ...not require any EA account! ...not require any database connection! ...NOT WORKS WITH STEAM CLIENTS so dont even try! ...not works at order in directories with fancy characters (like arabic, cyrillic, chinese or all non native latin characters like:áéőü and such!!!) ...not works without R11 Patch! ...not works in systems prior Win Xp (Supported: WINXP/WinServer/Win7/Win8.1(After dx and vcredist update) all works on both 32/64 bit) ...not require any advanced knowledge than this tutorial. ...emulates the master server accurately! ...not emulates friend system or server queue! ...NOT works with battlefield 3 or 4 *NOT* works! ...not have any punkbuster installed, cuz' it makes the servers disconnect, and never will include this into the pack. ...have an rcon tool but i did not set up, and i wont help with it, you have to figure it out! WARNING! The client/game, your Battlefield Bad Company 2 Install, itself refuses to connect to the MasterServer Emu if you have used >special characters< in the names of its directory/parent directories.(Thx Jesse Chang for the info) Its a Repacked server emulator(Mase Master server emu v0.8 + R34 Nexus client, but it wont need nexus, it is independent from nexus!) Roughly and blunt: you can make your own SMALL independent nexus emu clone with this! Compiled and setted up. There is not much to say about it , you can play BFBC2 on LAN if you want with friends. NO bots and as the things stated, wont will be soon... Only on Xbox has a gamemode named: onslaught, the ONLY mode what it has bots, but on PC there is not any not even the onslaught gamemode, there is only DM,RUSH,CONQUEST,SQDM,SQRUSH gamemodes. Just and only. so you will need pvp! It has the usual documents for gamemode and maps and manuals for setup game in !docs folder! Preqiusites(and some info): 0. Download Files from here: 1. you must install at least Microsoft Visual C++ 2010 SP1 Redistributable Package installed to run this. 2. There is no friends system, nor server queue, that part is not coded! in lan does not makes even a slightest sense... if u want a global play, go to nexus forums!) It uses flatfile and database files for store settings, so you wont need any mysql or mssql or similar, its WORKS WITHOUT THEM! The master emu stores the files for themself... 3. GLOBAL ranks not working(There is no sense under theese conditions) but the local and personal ranks and unlocks does works!! But be aware: YOU HAVE TO HAVE AT LEAST 4 PEOPLE IN YOUR SERVER TO GAIN XP!!! You can do this with either multiboxing(with software like sandboxie vm emulator if you have enough ram) and/or invite some friends. 4. in NAT forward theese ports (Both TCP and UDP): 80,9946,19021,19026,18390,18395,48888 to 48900,19567 to 19600 if u want to play public Internet game and/or lan :D 5. There is NO punkbuster in the server either, it has to been disabled and i did erased from the server cuz it was constantly kicked the people off and the emu is not supporting it.(even it was active regardless i did turned off thets why i erased it) 6. The relase is Hamachi and tunggle compatible for those who are not want to mess with the router and ports... just at the setup part give the server and client the hamachi IP 7. Domain names are supported, but instead of IP adress give your domain name in setup like: bc2.mydomain.com, or whatever your domain is...

Install: 1. Install game client(whatever with one, the server supports all 3 DLC and premium edition)

2. Install the R11 update!!!(thats important!!! and not part of the repack, since its 2.5 gb) It is can be found here: http://www.gamershell.com/download_79822.shtml

3. Extract the server into C:\ to look like this: C:\BC2EMU IT HAS TO BE LIKE THIS! Or else wont work the package!

4. From the server C:\BC2EMU\Client Crack folder copy dinput8.dll and bfb2c2.ini into the installed game's folder. (the server is 127.0.0.1 by default! you can change theese settings in bfb2c2.ini, and if you are want to make a public Master server emu search edit theese files: -

C:\BC2EMU\MasterServerEmu\config.ini - C:\BC2EMU\bfb2c2.ini - C:\BC2EMU\Client Crack\bfb2c2.ini
(This file ment to be in the client))

5. Go to the server's root folder and start "Start 4 Bad Company 2 Server.bat" ____ Will start 4 server instance on each category NOT neded the un limiter "Start 4 Vietnam Server.bat" / "Start ALL 8 Server.bat" -> WILL start every 8 gamemode It will start both Master server emu and the server itself.(if u have error messages, then check the server prerequisites section again!)

6. Go ingame, Click login, Create an account and solider, then click Multiplay and server browser, and you HAVE to refresh the list(until then will not shown the server). Play. Thats all, have fun! NOTE: if you want to ranks work: Open ./MasterServerEmu/config.ini and change the following lines:
all_stats_unlocked = true all_are_veteran = true And change the values to False!(both) but you will still need 4 people on the server to gain XP!! Have fun, and credit goes to all programmer of this script!